

# **Wave Arts Master Restoration Suite**



## **User Manual**

Last updated: April 27, 2007  
Copyright © 2007, Wave Arts, Inc. All Rights Reserved



# Table of Contents

1. Installation and Registration.....	5
1.1 Mac OS X Installation .....	5
1.2 Windows Installation .....	6
1.3 Registration .....	7
1.4 Registration Troubleshooting .....	10
2. Plug-in Control Operation .....	13
2.1 Knobs.....	13
2.2 Text Entry.....	13
2.3 Selector button.....	14
2.4 Sliders.....	15
2.5 Buttons .....	15
2.6 Output Meters .....	15
3. Menu Bar and Preset Manager .....	17
3.1 Bypass .....	17
3.2 Undo.....	17
3.3 Copy .....	17
3.4 A/B buffers .....	17
3.5 Preset name and arrow controls .....	18
3.6 Preset menu.....	18
3.7 Factory Presets.....	18
3.8 User Presets.....	19
3.9 Save... ..	19
3.10 Import.....	19
3.11 Export... ..	20
3.12 Reset... ..	20
3.13 Tools menu .....	20
3.14 About... ..	20
3.15 Open User Manual.....	21
3.16 Unlock Plug-in... ..	21
3.17 Check for Updates.....	22
3.18 Visit Website... ..	22
4. MR Hum.....	24
4.1 Overview .....	24
4.2 About Hum, Buzz, and Brickwall filtering .....	25
4.3 Using MR Hum.....	28
4.4 Parameters .....	30
4.5 Presets .....	32
4.6 Specifications .....	32
5. MR Click.....	33
5.1 Overview .....	33
5.2 About Clicks and Crackle.....	34
5.3 Using MR Click.....	36
5.4 Parameters .....	38
5.5 Presets .....	39
5.6 Specifications .....	39

## Wave Arts Master Restoration Suite

6. MR Noise .....	41
6.1 Overview .....	41
6.2 About Noise Reduction .....	42
6.3 Using MR Noise .....	45
6.4 Parameters .....	50
6.5 Presets .....	52
6.6 Specifications .....	53
7. MR Gate .....	55
7.1 Overview .....	55
7.2 About Gating .....	56
7.3 Using MR Gate .....	58
7.4 Parameters .....	58
7.5 Presets .....	59
7.6 Specifications .....	59
8. Master Restoration .....	61
8.1 Overview .....	61
8.2 Using Master Restoration .....	62
8.3 Presets .....	63
8.4 Specifications .....	63
License Agreement .....	65
Support .....	67
Index .....	69

# 1. Installation and Registration


## 1.1 Mac OS X Installation

If you are Installing from the Master Restoration Suite CD-ROM, insert the CD-ROM and double click the Master Restoration Suite OSX folder. You will see the "Master Restoration Suite OSX.mpkg" file as shown below. If you are installing from a download, the download manager will create a file "MasterRestoration.dmg". Double click on this file to create the file "Master Restoration.mpkg". If you are downloading and installing an individual plug-in or another bundle, the procedure is similar, but the files will be named after the plug-in or bundle rather than named "Master Restoration".




Now double click the "Master Restoration.mpkg" icon, and proceed though the installation process:

## Wave Arts Master Restoration Suite



### 1.2 Windows Installation

If you are installing from a CD-ROM, insert the CD-ROM and double-click the file "MasterRestoration.exe" shown below. This will start the installation process as described below. If you are downloading Power Suite, the file "MasterRestoration.exe" will be created on your computer. Double-click this file to start the installation process. If you are downloading and installing an individual plug-in or another bundle, the installation process is similar, but the files will be named after the individual plug-in or bundle rather than named "Master Restoration".



If you have downloaded the installer from the Wave Arts web site, when you run the installer you may get a warning message from Windows that the publisher could not be verified. Ignore the warning and click "Run" to continue.

## 1. Installation and Registration

The installer will guide you through the following screens:

1. **Welcome.** Click Next to continue.
2. **Read Me File.** Displays information about demo and registration procedure. Click Next to continue.
3. **License Agreement.** Read and click Yes if you agree to the terms of the agreement. The agreement is reprinted at the end of this user guide.
4. **Select Components.** Here you have the option to select DX, VST, and RTAS formats for installation. Click each box to toggle the checkmark on/off; boxes with checkmarks indicate the corresponding component (i.e., plug-in format) will be installed. By default, all three boxes are checked and thus all three formats will be installed. Click Next to continue.
5. **Choose Destination Location.** For each of the plug-in formats selected to install, choose the destination location on your file system. The first location is for DX format plugs, and also serves as the destination for the user manual. The second location is the folder where VST plug-ins are installed. The third location is the folder where RTAS plug-ins are installed. Click Next to continue.
6. **Select Program Manager Group.** Enter the name of the folder in the Windows start All Programs menu where the Wave Arts files can be accessed.
7. **Start Installation.** Click next to perform installation.
8. **Installation complete.** Click Finish to exit the installer. If you are attempting to install plug-ins that are currently in use, you may be asked to restart your computer.


### 1.3 Registration

After your plug-ins are installed, they will function in demo mode for 30 days. While in demo mode they will be fully functional, however you must register (i.e., unlock) your plug-ins or they will stop working after 30 days. You will be warned when you have 7 days remaining in your demo period.


To unlock the plugs after installation, go to <http://www.wavearts.com/register.html> and enter the required information. You'll need your **Serial Number** (either emailed to you or printed on a page in the product box), and your **Machine ID**, which can be determined by selecting the "About..." command in the Tools menu of any Wave Arts plug-in as shown in the figure below. The Machine ID is a number which identifies

## Wave Arts Master Restoration Suite

the computer you are using. Different computers will have different machine IDs.



After selecting the About... item you'll see an About dialog box like the one below. The About box shows the version number of the plug-in, the host plug-in format (e.g., DirectX, VST), the registration status of the plug-in, and the Machine ID of your computer. Make note of the Machine ID:



At our registration site (<http://www.wavearts.com/register.html>) you will enter your Serial Number (the number that begins with "WA-") and your Machine ID. If you purchased an electronic download, your Serial Number was emailed to you when you purchased the product. If you purchased the



## 1. Installation and Registration

software in a shrink-wrapped box, the Serial Number can be found in the box contents. The registration page has the following fields to fill out:

Name:

Email:

Serial Number:

Machine ID:

The registration page needs the following information: your name, your email address, your Serial Number, and your Machine ID. It's very important to provide a working email address because your Key Code will be emailed to this address. Also be sure to enter the Serial Number and Machine ID correctly.

Once the required information is entered at the Register web page you will be emailed a reply containing your 10-digit Key Code. An example reply is shown below:

Your key code for Wave Arts Master Restoration Suite for Machine ID 18869 is below:


38F40-B591D

To activate your software, go to the Unlock Plug-In item in the Tools menu of the plug-in and enter this number. A bundle can be registered by entering this key code in any plug-in included with the bundle.

Please contact us if you have any problems.


Thank you!  
Wave Arts, Inc.

You then unlock the plug-ins by selecting the Unlock Plug-In command in the Tools menu:



## Wave Arts Master Restoration Suite

Enter the Key Code in the dialog box:



You should see a dialog indicating that the registration was successful.

If you need to install the plug-ins on another machine, such as a laptop, you may repeat the procedure above. Our license policy permits up to three installations provided you are the only user. The registration web page keeps track of the number of machines on which you have installed your plugs. Each computer will have a different Machine ID.

When registering a bundle, such as Master Restoration Suite, you can obtain the Machine ID from any one of the plug-ins in the bundle, and you can enter the key code in any one of the plug-ins. If registration is successful, all the plug-ins in the bundle will be unlocked.

If you do not have web access, you can obtain a key code by calling Wave Arts customer support at 781-646-3794.

### 1.4 Registration Troubleshooting

**Invalid key code message** – make sure you are entering the 10-digit key code from the registration email, NOT the serial number that begins with "WA-". All letters should be uppercase, and you must enter the '-' character.

**Website says my number of registrations is used up** - contact Wave Arts support ([support@wavearts.com](mailto:support@wavearts.com)) and let us know the number of computer(s) the plug-ins are installed on. As a single user you can install the plug-ins on up to three computers, but additional users must purchase their own copies of the plug-ins.

**Key code email not received** - make sure the mail is not being filtered by a junk or SPAM mail program. The key code is mailed immediately and

## 1. Installation and Registration

should arrive in your email inbox within several minutes. Check your junk mail folder.

**Machine ID changed** - the Machine ID is based on your computer's network hardware (specifically, the MAC address of the computer's default internet adaptor). In normal circumstances this number will not change. However, if you change your network hardware or configuration, the Machine ID may change. If the Machine ID changes after the plug-ins have been unlocked, the plug-ins will display a message to this effect the next time they are opened. The plug-ins will then revert to 30-day demo mode to give you time to obtain a new unlock code based on the new Machine ID. In the case that the Machine ID is flipping between two values based upon two different network configurations, you can simply register both Machine IDs and the plug-ins will stay unlocked even if the Machine ID changes.



## 2. Plug-in Control Operation

### 2.1 Knobs



Please refer to the following guide for information about the various ways you can use knobs:

Function	Mac	Windows
Increase/Decrease a parameter value (rotate clockwise/counterclockwise)	Click on the knob + drag up/down	Click on the knob + drag up/down
Fine adjustment — increase/decrease	Shift + click + drag up/down  RTAS: Command + click	Right click + drag up/down -or- Shift + click + drag up/down  RTAS: Ctrl + click
Reset knob to default value	Command + click -or- Double-click  RTAS: Option + click	Control + click -or- Double-click  RTAS: Alt + click

### 2.2 Text Entry



Many value displays are editable text. A text field is editable if your mouse cursor changes to an I-beam when moved over the text. Following is a table that fully describes how to use the text editing features:

Function	Mac	Windows
Enter text entry mode	Click in the display	Click in the display
Select text	Click + drag	Click + drag
Select entire text	Double-click	Double-click
Delete character to left of cursor	Delete	Backspace
Delete character to right of cursor	Del	Delete

## Wave Arts Master Restoration Suite

Move the cursor left/right	Left/Right arrow keys	Left/Right arrow keys
Extend the current selection	Shift + click + drag -or- Shift + left/right arrow keys	Shift + click + drag -or- Shift + left/right arrow keys
Exit text entry mode	ESC* -or- Click outside value box -or- Tab -or- Return/Enter	ESC* -or- Click outside value box -or- Tab -or- Return/Enter
Select next parameter to edit	Tab	Tab
Select previous parameter to edit	Shift + Tab	Shift + Tab

\*Typing ESC causes the text to revert its original value before editing.

You'll find that many parameters, such as frequency, will recognize units typed into the text field. The following values, when typed into a frequency value box, are equivalent:

$$2k = 2 \text{ kHz} = 2000 = 2000 \text{ Hz}$$

### 2.3 Selector button




The selector button cycles through a number of fixed values. Click on the button to go to the next value. Click on the text to display a pop-up menu of the available values. The table below describes the functionality of the selector button:



Function	Mac	Windows
Go to next value	Click on the knob	Click on the knob
Go to previous value	Shift + click on knob	Shift + click on knob
Display pop-up menu of all choices	Click on text	Click on text

## 2. Plug-in Control Operation


### 2.4 Sliders

	Function	Mac	Windows
	Increase/Decrease a parameter value	Click on the slider handle + drag up/down	Click on the slider handle + drag up/down
	Fine adjustment — increase/decrease	Shift + click + drag up/down	Right click + drag up/down -or- Shift + click + drag up/down
	Reset slider to default value	Command + click -or- Double-click	Control + click -or- Double-click

### 2.5 Buttons

	Lighted buttons show a toggle state. A green, orange or yellow light indicates "on" and a black (extinguished) light indicates "off." Click the button to toggle the state.
	Buttons that do not light up are used to activate certain commands.

### 2.6 Output Meters

	Output meters show the peak signal power in short time updates — in green from -96dB to -6dB, in yellow between -6dB and 0dB, and in red above 0dB. Peak hold levels are also drawn. The meter also stores the overall peak value for each channel, and displays these values in the peak indicator boxes above the meter. If the detector finds a peak value above 0dB, the text color will turn red as a warning. Click on either indicator box to reset them back to -96dB. If the plug-in has an output gain knob, you can right click (PC) or Shift-click (Mac) on an indicator box to automatically increase or decrease the output gain so that the peak will be -0.1dB.
-------------------------------------------------------------------------------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------





## 3. Menu Bar and Preset Manager

All Wave Arts plug-ins in the Master Restoration Suite have the following menu bar displayed at the top of the plug-in:



This section describes the operation of the menu bar, preset manager, and the other functions available in the menus.

### 3.1 Bypass

Clicking on the bypass button bypasses the effect, that is, audio will pass through the effect without alteration. The button is lit when the effect is bypassed.

### 3.2 Undo

Clicking the Undo button causes the parameters to revert to their settings prior to the last edit. Only one level of undo is available, so clicking the undo button again will restore the parameters after the edit. Both A and B buffers (described below) have their own undo buffers.

### 3.3 Copy

Clicking the Copy button copies the current set of effect parameters to the unused A/B buffer. Hence, if the A buffer is currently selected, the parameters are copied to B, and if the B buffer is selected, the parameters are copied to A. After clicking Copy, you can continue to make changes, and then revert to the original copied settings by clicking either the A or B buttons to switch buffers.

### 3.4 A/B buffers

The A/B edit buffers allow you to compare two different sets of parameters or presets. One of the A or B buttons is always lit; the button that is lit shows the current buffer. Clicking either the A or B button will switch to using the other buffer, thus changing the effect settings (assuming different settings are stored in A and B).

Here's how to use the A/B buffers to compare two different presets. Select a preset from the Preset menu, then switch to the other buffer and select a different preset. Now switch between the two buffers to alternate between the two different presets.


### 3.5 Preset name and arrow controls

The currently selected preset name is displayed in the text field in the menu bar. Changing any parameters causes an asterisk (\*) to be displayed at the end of the name. This indicates that changes have been made to the preset. In order to save the changes to a user preset you must select the "Save..." item in the Preset menu, described below.

The arrow controls to the left and right of the preset name cycle through the set of factory and user presets. Clicking the right arrow goes to the next preset, clicking the left arrow goes to the previous preset.

### 3.6 Preset menu

The Preset menu contains lists of factory and user presets for easy selection, and options for managing presets. The functions are described in the following sections.



### 3.7 Factory Presets

Factory presets are selected from a rolloff menu at the top of the Preset menu. Factory presets cannot be modified or deleted. The Default preset is always first in the list; it defines all default parameter settings.

### 3.8 User Presets

User presets are selected from a rolloff menu just below the Factory presets in the Preset menu. When you first run a Wave Arts plug-in, there will not be any user presets and the menu will be empty. When you save a preset using the "Save" option the preset is added to the User menu. All instances of a plug-in share the same set of user presets. So, after you save a preset with one instance of a plug-in, you can go to another instance and find that the preset can be found in its User preset menu too.

You can delete an individual user preset by holding down the SHIFT key while selecting the preset. The entire set of user presets can be deleted using the Reset option, described below.

User presets are stored in a text file called "Master Restoration Presets.txt". On Macintosh, the presets are stored in the folder "/Library/Application Support/Wave Arts". On Windows the presets are stored in the folder "C:\Documents and Settings\All Users\Application Data\Wave Arts". If the preset file is deleted it will be created automatically by the plug-in. Note that all Master Restoration plug-ins share the same preset file; this is so presets created by the individual plug-ins are automatically shared with the Master Restoration plug-in.

### 3.9 Save...

When you have created an effect you want to save as a preset, select the "Save..." option. You will be asked to name the preset and the preset will be saved in the set of User presets. If you supply the same name as an existing user preset, the preset will be overwritten with the new preset without any warning notice.

### 3.10 Import...

User presets can be written to files using the "Export" function, and read from files using the "Import" function. Selecting the "Import..." option will first ask if you want to replace or merge the imported presets. Replacing causes your current set of user presets to be deleted and replaced with the presets read from the file, merging will add the presets read from the file to your set of User presets. Then you will be asked to choose a preset file for importing and the presets are read from the file.

Import can also be used to convert presets from an older version of the plug-in to the current version. If the plug-in detects presets from an older version and it knows how to convert them to the current version it will ask you if you want to convert the older presets to the current format.

## Wave Arts Master Restoration Suite

### 3.11 Export...

Selecting the “Export...” option will first ask if you want to replace or merge the exported presets. Replacing causes the presets in the file to be deleted and replaced with the exported user presets, merging will add the user presets to the presets in the file. Then you will be asked to choose a preset file for exporting and the presets are written to the file.


Preset Export is also useful for making backup copies of your user presets. If you have a large set of user presets, be sure to export them to a backup file.

### 3.12 Reset...

Reset is used to delete all of your user presets. Selecting “Reset...” will first ask you if you really want to do this, and if you confirm, all the user presets are deleted.

### 3.13 Tools menu

The Tools menu contains various important options, described below.



### 3.14 About...

The About option displays important information about your plug-in. An example is shown below:



On the top line, the plug-in name and version are displayed, along with the current plug-in format (DirectX, VST, AU, RTAS, or MAS). This is useful if you aren't sure which format of the plug you are running. The build date of the plug-in is displayed on the next line. The registration status is displayed on the next line. If the plug-in is operating in demo mode, the time remaining (if any) is displayed. If the plug-in has been successfully registered (unlocked), the key code and bundle name is displayed. The Machine ID of the computer is displayed on the next line. Finally, buttons are provided for opening the registration dialog and the user manual.

#### 3.15 Open User Manual...

Select this option to open the user manual in a browser. If the manual isn't found, you will be asked to navigate to it. Once the manual is opened successfully the plug-in remembers the location.

#### 3.16 Unlock Plug-in...

This option is described in the Installation and Registration chapter of this manual.

### 3.17 Check for Updates...

If you are connected to the internet, selecting this option will launch a browser and will navigate to the Wave Arts Downloads page.

### 3.18 Visit Website...

If you are connected to the internet, selecting this option will launch a browser and will navigate to the Wave Arts home page.



## 4. MR Hum



Figure 4-1. MR Hum user interface.

### 4.1 Overview

MR Hum combines hum removal, buzz removal, brickwall filtering, and spectrum analysis into one easy to use plug-in. The functions of MR Hum are also available in the Master Restoration plug-in. Here are some of MR Hum's key features:

- Hum removal using from 1 to 10 harmonic notch filters.
- Buzz removal for frequencies from 20 Hz to 200 Hz.
- Adjustable notch widths.
- Brickwall filtering for rumble and hiss removal.
- High resolution spectrum analysis.
- All sections can be monitored to hear removed signal.

MR Hum's audio routing and meter placement is shown in the diagram below:




Figure 4-2. MR Hum audio routing diagram.

The input signal is first processed by the spectrum analyzer, if set to "pre" mode. The input signal is then processed by the brickwall filter. This allows the user to



eliminate rumble using the low brickwall filter, or hiss using the high brickwall filter. The signal is next processed by the hum filter, which applies from 1 to 10 harmonic notch filters to cancel 50 Hz or 60 Hz hum and associated harmonics. The signal is next processed by the buzz removal filter. The result is input to the spectrum analyzer, if set to "post" mode.

When the monitor feature is enabled, the output consists of the signal that is removed by each of the enabled sections. For the low brickwall filter, the monitor will contain all frequencies up to the cutoff of the low brickwall. For the high brickwall, the signal will contain all frequencies above the cutoff of the high brickwall. For the hum filter, the monitor signal will contain only those frequencies that are notched by the hum filter; this is accomplished using a parallel sum of bandpass filters at the harmonics of the hum fundamental. For the buzz filter, the monitor signal will contain frequencies of the buzz fundamental and all harmonics.

### 4.2 About Hum, Buzz, and Brickwall filtering

#### Hum

Hum is caused by interference of audio circuitry with line power. Line power oscillates at either 50 Hz or 60 Hz depending on your world location. So in its simplest form, hum is a low frequency interference tone at either 50 Hz or 60 Hz. However, Hum often contains harmonics (multiples) of the fundamental frequency. For example, in a region with 60 Hz power, interfering hum would typically contain frequencies of 60 Hz, 120 Hz, 180 Hz, and so on. Below is a frequency spectrum of typical hum with a 60 Hz fundamental. It shows significant energy at 60 Hz, 120 Hz, 180 Hz, 300 Hz, and 420 Hz, i.e. the fundamental, 2d, 3d, 5<sup>th</sup>, and 7<sup>th</sup> harmonics.




Figure 4-3. Frequency spectrum of typical 60 Hz hum.

Hum is generally caused by poor grounding of audio equipment. Ground loops, where the ground connections between different pieces of equipment create a loop circuit, form a loop antenna which is effective at picking up line power oscillations. A typical ground loop can be created when two pieces of grounded equipment, say a pre-amp and an amplifier, are connected with a shielded audio connector that completes a ground loop. Ground loops can be broken by breaking the ground connection on the audio path. It is also possible to lift the ground connection of a piece of equipment, but this is a dangerous practice because it eliminates the safety feature of a ground, which is to prevent electrocution. Even without ground loops, hum can be created when sensitive audio electronics share a ground with other equipment that may be discharging significant current through the ground. Hum harmonics are created when electronic equipment rectifies AC power to create DC, or by other devices such as dimmers.

Hum is best removed by using a set of sharp notch filters to eliminate the fundamental and harmonic frequencies of the hum. Sharp notch filters work well because the frequency of line power is very stable so the filters can be very narrowly tuned. MR Hum uses up to 10 notch filters to eliminate up to the 10<sup>th</sup> harmonic.

The frequency of hum depends on the frequency of the local line power. 60 Hz power is used in North America (except Greenland), Central America, most of South America, Saudi Arabia, and parts of southeast Asia including Korea. The rest of the world, including Europe, Asia, Africa, and Australia uses 50 Hz power.

### Buzz

Buzz is a periodic impulsive contamination which like hum can be caused by poor grounding. The simplest example of a buzz is that of a very bad hum whose harmonics extend up to very high frequencies. However, buzz can also be caused by a periodic signal, like a camera motor, which is recorded along with the audio program. The plot below shows buzz created by very poor grounding with 60 Hz line power. The periodicity of the signal is about 16.7 msec.




Figure 4-4. Time plot of 60 Hz buzz.

Buzz removal differs from hum removal in that the buzz harmonics extend to high frequencies, and the fundamental frequency might be something other than 50 or 60 Hz. Buzz processing consists of a set of notch filters located at the fundamental buzz frequency and at all harmonics in the audio range. The set of notch filters is created using a "comb filter" which essentially computes the difference of the input signal with a copy of the input signal delayed by one fundamental period. The difference calculation removes any periodic contamination. However, the side effect imparted to the signal is that of a comb filter, that is, an echo with a very short delay. This can sound like a hollow room ambience and may be objectionable. Hence, buzz removal imparts significant side effects.

### Brickwall filters

Brickwall filters are lowpass or highpass filters with very steep cutoffs, used to pass all frequencies up to the cutoff frequency and eliminate all frequencies beyond the cutoff. The frequency range that is passed unaltered is called the "passband", the frequency range that is attenuated is called the "stopband". MR Hum's brickwall filters are implemented using 10th order elliptical filters, with at least 90 dB of stopband attenuation and less than 0.1 dB of passband ripple.

## Wave Arts Master Restoration Suite

Brickwall filters are used to eliminate unwanted frequency ranges. One use of the low brickwall filter is to eliminate low frequency rumble which can occur from phonograph playback or due to wind or other low frequency noise during an acoustic recording. Brickwall filters can also be used when processing a noisy recording of an instrument sound that does not use the entire frequency range. The brickwall filter would be positioned at the edge of the instrument's frequency range to eliminate out-of-band noise. So for example, when processing voice, one could use the brickwall filters to eliminate all frequencies below 100 Hz and above 8 kHz.

The brickwall filters can also be used to zero in on a particular frequency range just for analysis purposes. For example, one could use the brickwall filters to listen to selected overtones in an organ, or to isolate the sibilants of a human voice.

### 4.3 Using MR Hum

MR Hum has three sections: the hum filter, the buzz filter, and the brickwall filters. Each section can be enabled with the corresponding ENABLE button. Hence the enable buttons can be used to compare the results of processing enabled with processing disabled (bypassed). The monitor feature is also extremely useful to tune the parameters by listening. The spectrum analyzer can be used to visualize the spectrum before and after processing.

#### Spectrum analysis

Spectrum analysis works by transforming the time signal into its constituent frequencies and displaying the resulting spectrum amplitudes as a function of frequency. You can see at a glance what frequencies are present in your signal. MR Hum uses a long time window when transforming blocks of the input signal; hence the resulting spectrum has very good resolution at low frequencies which makes it easy to see low frequency tones as spikes in the spectrum. See figure 4-2 for an example of a spectrum display. Because of the long time block sizes, the update rate is fairly slow, just a few updates per second. When using the spectrum analyzer to visualize hum or buzz, it is best to audition a portion of your signal which contains only the hum or buzz.

MR Hum spectrum analysis can be set to "pre" mode, meaning it runs before hum processing, or "post" mode, meaning it runs after hum processing; see figure 4-1. You can select between the two modes by SHIFT-clicking (right-clicking on Windows) on the vertical axis of the display; this causes a popup menu to appear containing the two choices. By default the post mode is selected. The vertical range of the spectrum analysis is fixed: the bottom of the display is -120 dB and the top of the display is 0 dB, hence each division is 15 dB.

#### Brickwall

Each of the low and high brickwall filters has an enable button and a knob for setting the cutoff frequency. When one of the bands is enabled, a corresponding brickwall control handle appears in the frequency response display. You can edit the

brickwall frequency by dragging the control handle or dragging the frequency knob. The monitor feature can be used to hear the signals that are removed by the brickwall filters. If both the low and high brickwall filters are enabled, the monitor signal will contain both low and high frequencies.

### Hum

If your signal has an obvious hum, the first place to start is to enable the Hum section, then select either the 50 Hz or 60 Hz hum preset depending on the frequency of the hum. In the case where you are processing a signal of unknown origin, you should be able to see the fundamental of the hum frequency in the spectrum analysis display. You can also hear the hum frequency using the monitor feature. Press the MONITOR button to enable monitoring. This will pass only the frequencies of the hum fundamental and the selected harmonics. Then alternately select the 50 Hz or 60 Hz preset. One of these will pass the hum.

The default width is 1 Hz. This is the bandwidth of the notch filters defined as the width between the half-power frequencies. Hence, with a width of 1 Hz, the notch at 60 Hz will have half power (-3 dB) response at 59.5 Hz and 60.5 Hz. Obviously these filters are very sharp. The notches are infinite depth; at the center frequency the response is 0 which equals -inf dB.

Very narrow width filters have a long time response. Consequently, a narrow notch filter will take some time to reject the hum. When applying the hum filter to a signal with hum, if you notice that the hum persists at the very start of the signal, you can increase the width of the notch filters and this will make the filters respond faster to the onset of the hum.

Deciding how many harmonics should be used can be done by examining the spectrum display which is overlaid with the hum frequency response showing the notch filters. As you increase the number of harmonics you can see if the spectrum has a corresponding spike at that frequency. If there is no corresponding spike in the spectrum, then the newly added notch will have little effect. In some cases you may have to use a large number of notches in order to cancel a high order harmonic. For example, in Fig 4-3, one would select 7 harmonics in order to reach the 7<sup>th</sup> harmonic which has significant energy. Although the 4<sup>th</sup> harmonic of the hum is not present, there is no way to disable the 4<sup>th</sup> harmonic of the notch filter.

One can also listen to the harmonics using the monitor feature. With monitor enabled, try increasing the number of harmonics starting with 1. If adding harmonics does not increase the amount of hum in the monitor signal, then you should not add harmonics. You may also notice frequencies from the desired signal appearing in the monitor. This indicates frequencies that will be cut by the hum filter. While monitoring, you should select the number of harmonics that maximize the monitored hum signal while minimizing the amount of desired signal.

## Wave Arts Master Restoration Suite

The frequency response of the hum filter is shown in the MR Hum display. This reflects the fundamental frequency, the number of harmonics, and the width of the notch filters. However, the parameters cannot be edited by clicking in the display.

### Buzz

If the hum is bright and buzzy, you should try processing with the buzz filter instead. In this case you should disable the hum filter. The buzz filter can also be used for any sort of periodic contamination. After enabling the buzz section, the first step is to determine the buzz frequency. If you know the buzz is created by line power, then enter the fundamental in the buzz frequency control by adjusting the knob or by typing in the value. You can also examine the spectrum display and look at the frequency of the buzz fundamental. You can also use the monitor feature while slowly adjusting the frequency to scan for the proper fundamental. When the frequency parameter is adjusted close to the fundamental, the monitor will begin to pass the buzz sound. Similarly, with monitoring off and with the spectrum analysis set to "post" mode, you can scan for the buzz fundamental and see when the buzz harmonics are canceled by the buzz filter; this should be plainly audible as well.

Once the fundamental is determined, turn off the monitor and proceed to adjust the width control. Generally, larger widths will reduce the resonant sound of the comb filter. Now try enabling/disabling the buzz section to hear the effect of the buzz processing. It's possible the comb filter effect imparted by the buzz filter is more annoying than the buzz. If so, you can seek other methods to remove the buzz. Broadband noise reduction as provided by MR Noise can be extremely effective in removing buzz. Also the buzz can be gated in quiet sections using MR Gate.

## 4.4 Parameters

The table below lists all the internal parameters of MR Hum and shows the range of values as would be displayed by a generic parameter-value plug-in interface. Most of these parameters have a one to one correspondence with controls on the user interface.

Parameter name	Values
Enable	0 = Off, 1 = On
Monitor Enable	0 = Off, 1 = On
Brickwall Low Enable	0 = Off, 1 = On
Brickwall Low Freq	20 - 20000 Hz
Brickwall High Enable	0 = Off, 1 = On
Brickwall High Freq	20 - 20000 Hz
Hum Enable	0 = Off, 1 = On
Hum Frequency	20 - 200 Hz
Hum Width	0.1 to 10 Hz
Hum Num Harmonics	1 - 10
Buzz Enable	0 = Off, 1 = On

## 4. MR Hum

Buzz Frequency	20 – 200 Hz
Buzz Width	10 – 100 Hz
Gain	-12 to +12 dB
Monitor Gain	-12 to +12 dB

The parameters are described in more detail below.

**Enable** — This parameter is only available in the standalone MR Hum, where it functions as the global bypass control. The Master Restoration plug-in does not display an enable control for the Hum&Buzz section and the Hum&Buzz section is always enabled.

**Monitor Enable** — This enables/disables the monitor feature. When monitoring is enabled, the output signal consists of all the signals that would be removed by the MR Hum filters.

**Brickwall Low Enable** — Enables or bypasses the brickwall lowpass filter.

**Brickwall Low Freq** — Sets the brickwall lowpass filter cutoff.

**Brickwall High Enable** — Enables or bypasses the highpass brickwall filter.

**Brickwall High Freq** — Sets the brickwall highpass filter cutoff.

**Hum Enable** — Enables/disables the hum removal filter.

**Hum Frequency** — This parameter sets the fundamental frequency of the hum, from 20 to 200 Hz. Typically you will use 50 Hz or 60 Hz which can be selected using the presets.

**Hum Width** — This parameter sets the bandwidth of the hum notch filters in Hz, where bandwidth is defined as the difference between the half-power (-3 dB) points of the notch response.

**Hum Num Harmonics** — Sets the number of notch filters used in the hum filter, from 1 to 10. This should be set to the number of prominent harmonics in the hum for maximum cancellation.

**Buzz Enable** — Enables/disabled the buzz removal filter.

**Buzz Frequency** — This parameter sets the fundamental frequency of the buzz, ranging from 20 to 200 Hz.

**Buzz Width** — This parameter sets the bandwidth of the buzz notch filters in Hz, where bandwidth is defined as the difference between the half-power (-3 dB) points of the notch response.

**Gain** — Output gain in dB.

## Wave Arts Master Restoration Suite

**Monitor Gain** — Monitor output gain in dB.

### 4.5 Presets

MR Hum factory presets are listed in the table below. In the standalone plug-in these appear in the preset menu in the menu bar. In Master Restoration, these presets appear in the Hum&Buzz Preset selector.

Name	Description
Default	Default settings, 60 Hz hum removal
60 Hz Hum	60 Hz hum removal
50 Hz Hum	50 Hz hum removal
60 Hz Buzz	60 Hz buzz removal
50 Hz Buzz	50 Hz buzz removal
Rumble	Low frequency rumble filter
Speech band	Isolate speech range

### 4.6 Specifications

<b>Description</b>	Hum and buzz suppression filters, brickwall filters for rumble and hiss suppression, and spectrum analysis
<b>Platforms</b>	Pentium & compatible; PowerPC
<b>Operating Systems</b>	Windows 2000/XP; Mac OS X 10.4 or higher
<b>Plug-in Formats</b>	AU, DirectX, MAS, RTAS, VST
<b>Sampling Rates</b>	up to 192 kHz
<b>Precision</b>	64-bit hum and brickwall filters, 32-bit buzz filtering
<b>Latency</b>	none
<b>I/O Formats</b>	mono-mono, stereo-stereo



## 5. MR Click



Figure 5-1. MR Click user interface.

### 5.1 Overview

MR Click combines click and crackle filtering specifically intended for restoring phonograph recordings. The functions of MR Click are also implemented as part of the Master Restoration plug-in. Some of MR Click's features include:

- Separate algorithms optimized for click and crackle processing.
- Sophisticated detection algorithms for clicks and crackle focus processing on contaminating events.
- Onset detection allows crackle processing to bypass onset events, keeping attacks bright.
- Monitoring feature for hearing eliminated clicks and crackle.
- Comprehensive stereo display of signal level, clicks, crackle, and onset events.

A diagram of MR Click's audio routing and meter placement is shown below.




Figure 5-2. MR Click audio routing diagram.

The input signal is processed by the click filter first, then the crackle filter. When the monitor feature is enabled, the output consists of the signal that is removed by each of the enabled sections. If both the click and crackle processors are enabled, the monitor signal will contain both removed clicks and crackle.

### 5.2 About Clicks and Crackle

The playback of phonograph recordings often contains noticeable clicks and crackle caused by degradation of the recording grooves, surface scratches, or accumulation of foreign matter in the grooves. We use the term “click” to mean a large disturbance, such as caused by a scratch or an obstruction in the groove. Clicks might also be called pops. The disturbance that causes a click is always so large that both stereo channels will be similarly affected. We use the term “crackle” to mean the frequently occurring, lower amplitude disturbances due to groove degradation or accumulated dust. These are small enough to affect just one wall of the recording groove, and hence crackles will often occur on just one stereo channel at a time.

The plot below shows a typical phonograph click. The click is considerably louder than the surrounding signal.




Figure 5-3. Plot of a vinyl phonograph click during a signal. Only one channel is shown; however both channels were affected by the click event.

Clicks may also be present in digital audio signals that have undergone some kind of error in transmission or processing. If the contamination results in various samples taking on random values, these will sound similar to phonograph clicks and can be effectively suppressed using MR Click.

#### 4. MR Click

The plot below shows a typical phonograph crackle event. Although not shown, this crackle event affects only one channel. The level of the crackle is similar to the level of the surrounding signal. Typical crackle events have a shorter duration than clicks and have a correspondingly higher frequency content.




Figure 5-4. Time plot of a vinyl phonograph crackle event. Only one channel is shown, and only one channel was affected by the crackle event.

#### Processing clicks and crackle

The strategy for processing clicks and crackle is to detect the occurrence of click and crackle events, and then alter the signal around the event to suppress the sound of the click or crackle. Both the detection strategy and the suppression strategy differ for click and crackle events.

Clicks are detected as a rapid onset and offset of energy. Clicks are suppressed by overwriting the signal with a linear interpolation during the click event. The time of the interpolation is a user parameter; typically 1 msec is ample to completely mask the click.

Crackle is detected as a rapid onset of high frequency energy. Crackle is suppressed by smoothing the signal around the crackle event using a lowpass filter.

In many cases, crackle caused by degradation of the phonograph groove is not distinguishable from the content of the original recording. Typical percussive events, such as snare drum hits, ride cymbal hits, etc., contain rapid onsets of high frequency energy that are indistinguishable from crackle events. If the crackle processing was applied uniformly, the percussive attacks would be dulled by the crackle smoothing. To alleviate this problem, MR click has an option to bypass crackle processing during note onsets. MR Click contains a broadband onset

## Wave Arts Master Restoration Suite

detector that will trigger on note onsets. When the bypass onsets option is engaged, the crackle processing will be bypassed during note onsets.

### 5.3 Using MR Click

#### MR Click Display

Operation of MR Click is greatly facilitated by the event display shown below:



Figure 5-5. Click and Crackle event display. The green plot shows signal level, red lines are clicks, yellow lines are crackle, and grey lines are onset events.

The display is active when MR Click is enabled. The display shows the past few seconds of signal history and scrolls from right to left as audio playback proceeds. The green plot shows input signal level. Red lines indicate detected click events. Yellow lines indicate detected crackle events. White lines indicate detected onset events. These are summarized in the table below.

<b>Green</b>	Input signal level
<b>Red</b>	Click events
<b>Yellow</b>	Crackle events
<b>Grey</b>	Onset events

Click events are shown only if the click processor is enabled. Crackle and onset events are shown only if the crackle processor is enabled.

To change the time range, right-click (SHIFT-click on Mac) the horizontal time axis and a popup menu will appear with different choices for the time range in seconds. To change the vertical range, right-click (SHIFT-click on Mac) the vertical amplitude axis and a popup menu will appear with different choices for the amplitude range in dB.

### MR Click Operation

When processing phonograph recordings to remove clicks and crackle, the strategy is to first remove the loud clicks and pops and then remove the lower level crackle.

You should first audition the material to be processed and listen for offending clicks. Then, rewind your track and enable the click processor by clicking on the **ENABLE** button. Start playback of the track and adjust the click threshold knob until all the offending clicks are detected. Lower threshold values will detect more click events, and higher threshold values will detect fewer click events (only the loudest clicks will be detected at high threshold settings). You can see the clicks appear in the event display as red lines. You can also enable the monitor feature and listen to the detected clicks in the monitor signal. When the monitor feature is off, you can also enable/disable the click processor to compare the results of click removal versus no processing.

A click duration of 1 msec usually works well, but in some cases you might want to lengthen the duration, if there is still a residual thump sound after click removal.

Once you are satisfied that the loud clicks and pops have been suppressed, you can proceed to process the crackle. Again, it is good to audition the track ahead of time to get a good idea of the amount of crackle present. Then enable the crackle processor and begin playback. You will see the detected crackle events appear as yellow lines in the display. Adjust the threshold to change the number of crackle events detected; lower thresholds will detect fainter crackle and will create more crackle events, while higher thresholds will detect louder crackle and will create fewer crackle events.

The monitor feature is particularly useful for hearing the detected and removed crackle events. Note that if the click processor is still engaged you will also hear the removed click events. With lower thresholds, the crackle processor will detect high frequency portions of your signal and process these as crackle; this will be apparent when monitoring because you will be able to hear parts of your signal in the monitor signal. This is a good indication that the threshold is set too low. Basically, the monitored crackle signal should sound like random crackle events and should not resemble your input signal. If your signal is fairly percussive, it is likely that the crackle processor will detect the percussive onsets as crackle events. This will be audible in the monitor signal because you will hear the underlying rhythm. Your choices here are to increase the threshold, or to engage the onset bypass mechanism.

To use the onset bypass, adjust the onset threshold until you see onset events (white lines in the display) that correspond to the underlying rhythm of your track. Lower thresholds result in more onset events; higher thresholds reduce the number of onset events. Now enable the onset bypass by clicking on the **BYPASS** button. When monitored, you should hear that the crackles corresponding to musical onsets are no longer present, or at least reduced, when the onset bypass is engaged.

It is unrealistic to expect that you will be able to remove all audible clicks and crackle without adversely affecting the sound of the original signal. A better strategy is to remove the most offending events, leaving the signal as untouched as possible. Because crackle is most audible during silent portions, say between tracks, one might be tempted to lower the threshold until all of the crackle is suppressed during these silent portions. But this is probably overdoing it, and there are other techniques which can be used to clean up the quiet portions. Both broadband noise reduction, as provided by MR Noise, and noise gating, as provided by MR Gate, can clean up the quiet portions. Hence you should focus on removing the clicks and crackle that are audible while the music is playing.

### 5.4 Parameters

The table below lists all the internal parameters of MR Click and shows the range of values as would be displayed by a generic parameter-value plug-in interface. Most of these parameters have a one to one correspondence with controls on the user interface.

Parameter name	Values
Enable	0 = Off, 1 = On
Monitor Enable	0 = Off, 1 = On
Click Enable	0 = Off, 1 = On
Click Threshold	6 – 20 dB
Click Duration	0.5 – 10 msec
Crackle Enable	0 = Off, 1 = On
Crackle Threshold	12 – 40 dB
Onset Bypass	0 = Off, 1 = On
Onset Threshold	0 – 40 dB
Gain	-12 to +12 dB
Monitor Gain	-12 to +12 dB

The parameters are described in more detail below.

**Enable** — This parameter is only available in the standalone MR Click, where it functions as the global bypass control. The Master Restoration plug-in does not have an enable for the Click & Crackle section.

**Monitor Enable** — This enables/disables the monitor feature. When monitoring is enabled, the output signal consists of the click and crackle signals that are removed by MR Click.

**Click Enable** — Enables or bypasses the click processor.

**Click Threshold** — Sets the click detection threshold. Lower values result in many faint clicks detected, high values result in only a few loud clicks detected.

## 4. MR Click

**Click Duration** — Sets the interpolation time for each click. MR Click will overwrite the click event with a linear interpolation starting 0.5 msec before the click and lasting a duration set by this parameter.

**Crackle Enable** — Enables/disables the crackle removal filter.

**Crackle Threshold** — This parameter sets the crackle detection threshold. Lower values result in many faint crackles detected, high values result in only a few loud crackles detected.

**Onset Bypass** — When onset bypass is engaged, crackle processing is bypassed during detected onset events. This is useful to prevent decrackling of percussive onsets that can easily be recognized as crackle.

**Onset Threshold** — This parameter sets the onset detection threshold. Lower values result in many faint onsets detected, high values result in only a few loud onsets detected.

**Gain** — Output gain in dB.

**Monitor Gain** — Monitor output gain in dB.

## 5.5 Presets

MR Click factory presets are listed in the table below. In the standalone plug-in these appear in the preset menu in the menu bar. In Master Restoration, these presets appear in the Click & Crackle Preset selector.

Name	Description
Default	Default settings with nothing enabled
Vinyl Clean	Typical vinyl phonograph settings, both click and crackle
Vinyl Light Clean	Light cleaning settings for vinyl
Vinyl Hard Clean	Hard cleaning settings for vinyl
Clicks	Click removal
Crackle	Crackle removal

## 5.6 Specifications

<b>Description</b>	Click and crackle removal filters
<b>Platforms</b>	Pentium & compatible; PowerPC
<b>Operating Systems</b>	Windows 2000/XP; Mac OS X 10.4 or higher
<b>Plug-in Formats</b>	AU, DirectX, MAS, RTAS, VST

## Wave Arts Master Restoration Suite

<b>Sampling Rates</b>	up to 192 kHz
<b>Precision</b>	32-bit
<b>Latency</b>	click: 10.5 milliseconds when enabled crackle: 3 milliseconds when enabled
<b>I/O Formats</b>	mono-mono, stereo-stereo



## 6. MR Noise



Figure 6-1. MR Noise user interface.

### 6.1 Overview

MR Noise is broadband noise reduction processor. Here are some of MR Noise's key features:

- Great sounding with minimal artifacts.
- Low latency (under 20 msec) noise reduction can be used in live situations.
- Fast noise floor learning time (down to 50 msec), hence noise looping is not required.
- Auto dynamics mode keeps transients sharp while avoiding squirrely artifacts.
- Monitor feature to hear removed noise.
- Very easy to use.
- Comprehensive display shows spectrum of input signal, output signal and noise floor.
- Parameters can be edited as function of frequency.

## Wave Arts Master Restoration Suite

A diagram of MR Noise's audio routing and meter placement is shown below.




Figure 6-2. Audio routing in MR Noise.

In normal processing, the noise processor removes noise from the signal and outputs the noise reduced signal. When the monitor feature is enabled, the output consists of the signal, i.e. the noise, that is removed by the noise processor.

## 6.2 About Noise Reduction

### Noise

Noise is a general term that can apply to various types of unwanted artifacts in an audio signal, including hum, buzz, clicks, crackle, rumble, and hiss. We use the term "broadband noise" to describe noise consisting of a random signal which sounds like hiss. This type of noise is present in every audio signal. There are many sources of broadband noise:

**Digital quantization** – in digital signals, the quantization of the signal to a certain bit resolution creates broadband noise called quantization noise.

**Acoustic recordings** – there is always some acoustic noise, which can be due to ventilation sounds or other background noises.

**Electronics** – all electronics, particularly high gain amplifiers, will add noise to a signal due to thermal variation in the amplifier elements.

**Magnetic tape recordings** – magnetic tape is composed of individual grains of magnetic material which are each magnetized differently to record an audio signal. The finite number of grains and limited tape speed causes random noise during playback.

**Phonograph recordings** – surface irregularities cause playback noise.

An important characteristic of the noise is its spectrum, that is, the distribution of energy at different frequencies. The noise spectrum is also called the noise "floor", because it defines the lowest signal level at each frequency that can be distinguished from the noise. In order for a signal to be audible, it has to be above the noise floor. The noise floor is also called the noise "profile" in other noise reduction literature.

For many sources of noise, the noise floor spectrum will remain fairly constant over time. This is typical of quantization noise, electronic noise, magnetic tape noise,

and phonograph noise. Acoustic noise, however, can either be constant or varying. We would expect the acoustic noise in a quiet recording room to be fairly constant. But the acoustic noise in an outdoor environment can vary significantly over time due to traffic noise, wind, or other background sound.

### Noise reduction

The noise reduction algorithm used by MR Noise is very effective at removing noise with a constant spectrum. The MR Noise algorithm operates in the frequency domain. At each frequency, it compares the signal level with the noise floor. If the signal level is well above the noise floor, it is unchanged, but signals that are close to the noise floor are attenuated. This is like having a noise gate running at each frequency, where the gate threshold is set to the noise floor level at that frequency.

### Learning the noise floor

MR Noise must first learn the noise floor spectrum. This is done by finding a portion of the recording where there is just noise without signal. The noise sample is played through MR Noise with the LEARN option enabled. When learning, MR Noise computes the noise spectrum, and when learning is complete, MR Noise remembers this spectrum and uses it for subsequent noise removal. The MR Noise algorithm requires only a short noise sample, down to 50 msec, to learn the noise spectrum effectively, although longer learning times give more accurate results.

To handle varying noise floors, there are two approaches. One can learn a long varying portion of noise and use this average floor, or one can segment the audio into different clips and learn different noise floors for each clip. The latter method is more effective.

### Reduction amount

It is often necessary to limit the maximum amount of attenuation. This is done via the Amount parameter, which specifies the maximum attenuation. By limiting the maximum attenuation, we limit the amount of noise reduction, but also limit processing artifacts.

### Knee shape

As described above, the noise reduction algorithm is essentially a dynamics processor applied to each frequency band in the spectrum. Maximum attenuation is applied when the signal level falls equal (or below) the noise floor. Signal levels above the noise floor are attenuated less because they are less likely to be noise. When the signal rises to about 20 dB over the noise floor, there is very little attenuation, since it is very unlikely the signal could be noise. So this is like a gate or expander dynamics curve where there is no attenuation at high signal levels with respect to the noise, but attenuation is applied as the signal level gets lower. In the MR Noise algorithm, the curve of attenuation versus level above noise floor is defined by the Knee parameter. There are three knee shapes: soft, medium, and

## Wave Arts Master Restoration Suite

hard. These actually represent well defined theoretical approaches to noise reduction: Soft is spectral magnitude subtraction, Medium is Wiener filtering, and Hard is spectral power subtraction. But we can also think of them as just different knee shapes that control how fast the attenuation is applied as the signal approaches the noise floor.




Figure 6-3. Plots of attenuation as a function of level in dB above the noise floor. The three knee shapes are shown: red dashed = Soft, blue dotted = Medium, green solid = Hard.

## Musical noise

If the noise reduction is applied to noise alone, then portions of the noise will survive the noise reduction processing because by chance they are distributed above the average noise floor. The result is a set of tone bursts occurring at random times and frequencies, called *musical noise*, which despite being an interesting phenomenon, also sounds fairly annoying. It sounds like trickling water, but with lots of resonance, as if one was listening to it through a tube. In order to prevent musical noise from occurring it is necessary to raise the knee point above the noise floor so that more attenuation is applied to signals just above the noise floor. In the MR Noise plug-in, the Threshold parameter specifies an offset that raises the knee point above the noise floor. About 6-9 dB of noise floor offset is usually sufficient to completely silence any musical noise.

## Dynamics

Another artifact of noise reduction is the possibility of individual harmonics turning on and off as they decay approaching the noise floor. We can reduce the possibility of individual frequencies gating on and off by introducing some time dependent filtering to each frequency gain, in the form of attack and release rate controls. The release control determines the maximum rate of attenuation for decaying signals.

The attack control determines the maximum rate of boost for increasing signals. Using short attack and release times means the frequency band gains will respond very quickly to the input signal. Using longer attack and release times means the frequency band gains will respond slower to changing inputs.

### 6.3 Using MR Noise

#### Learning the noise floor

The first step is to identify a section of your track that contains only background noise. Often this can be found at the very start of the track before the signal comes in. However, if the track has already been cropped to eliminate leading and trailing signal, then you will have to find noise during a silent section in the track. MR Noise can learn a noise profile with as little as 50 msec of noise, so this could be found between words in a dialog track for example. If you can't find any part of the track which is quiet then the noise floor will have to be estimated by learning the quietest portion you can find and then manually editing the floor parameters to lower and smooth the floor. Editing the noise floor is described later.



Figure 6-4. Learn time and Learn button.

The learn time is specified using the LEARN TIME parameter. It has various choices from 50 msec to 5 seconds, and also has a manual mode. Manual mode would be used for doing very long averages. Choose the longest learn time that is shorter than the portion of noise you have identified.

If you are using the Master Restoration plug-in, first enable the noise section by clicking on the ENABLE button. If you are using the MR Noise plug-in it should already be enabled unless it happens to be bypassed, in which case you should turn off the bypass.

Now click the LEARN button. It will light in a lovely purple color. Now start playback of your track. During learning you can see the noise floor evolve in the spectrum display as the averaging takes place. When learning is complete the LEARN button will extinguish and the displayed noise floor spectrum is smoothed as it is converted from a spectrum to a set of 31 noise floor parameters spaced at 1/3-octave bands. For stereo inputs, MR Noise learns independent noise floors for the left and right channels.

At this point the noise reduction is active. You can adjust the noise reduction parameters as described below.

## Wave Arts Master Restoration Suite

Manual learning can be used for learning very long portions of noise, or for controlling the start of learning. When the LEARN TIME is set to Manual, learning will continue for as long as the LEARN button is on. You must click LEARN again to turn off learning.

### Adjusting the noise reduction

Assuming you are starting from the default preset values, the noise reduction parameters will be set to something sensible. Recommended parameters are: AUTO mode enabled, Soft Knee type, Threshold from 6 to 9 dB to eliminate musical noise, and Amount from 3 to 40 dB based on preference.

Adjusting the Threshold can be done easily if you have a quiet portion of the track that contains only noise. When this is processed adjust the threshold as low as possible until you hear some musical noise (random tones), and then raise the threshold by 2-3 dB so the tones disappear.

The Amount control is the most important for adjusting the tradeoff between noise reduction and processing artifacts. When Amount is set to 0 dB, there is no noise reduction and the output signal should exactly match the input. Increasing the Amount increases the amount of noise reduction, but also increases the possibility of processing artifacts. Possible processing artifacts include:

- smearing of attack transients,
- harmonic tones gating on and off, causing a watery effect,
- musical noise during quite portions,
- loss of signal content, particularly at high frequencies.

MR Noise is designed to minimize artifacts and give you really great noise reduction performance. But you may encounter difficult input signals that can reveal artifacts under heavy noise reduction. Using moderate Amounts, say 6-12 dB, can leave a bit of noise in your recordings, but this may be more desirable than trying to fully suppress noise and causing artifacts.

Another useful technique when processing extremely noisy recordings is to do multiple passes. Instead of doing one pass with a large amount of noise reduction, do several passes using gentle noise reduction settings. This technique will usually result in fewer bad sounding artifacts.

Sometimes a large Amount value is needed to fully suppress noise during quiet portions. However, it may be better to focus instead on what sounds best when the music is playing. Suppressing noise during quiet portions can also be done using a basic noise gate, such as MR Gate.

### Adjusting attack and release times

For transient input sounds with sharp attacks you will want to use short attack and release times to preserve the transients. For slower changing legato sounds, you want to use long attack and release times to prevent harmonics from gating on and off rapidly as they decay near the noise floor. If the attacks seem to be smoothed out by the noise reduction, try using a faster attack time. If you hear individual harmonics gating on and off as they decay, try using a longer release time.

### Auto dynamics mode

MR Noise features an AUTO dynamics mode that adjusts the attack and release times based upon transients in the input signal. When AUTO mode is enabled, MR Noise detects transients in the input signal and automatically uses short attack time during rapid onset events and uses short release times during rapid offset events. When there are no transients, MR Noise uses the attack and release times set by the user for maximum smoothness during slowly changing passages. We recommend enabling AUTO mode at all times.

### Monitoring the removed signal

Enabling the MONITOR feature allows you to hear the signal that is being removed by the noise reduction processor. Ideally this would contain only noise, but in practice it is impossible to perfectly separate the unwanted noise from the desired signal, hence the monitor signal will contain some residue from your desired signal, usually at high frequencies and during transients. Listening to the monitor can be useful for adjusting the various parameters to optimize the noise reduction performance. Adjusting the Amount parameter directly controls the amount of noise signal you will hear in the monitor. Increasing the Amount also increases the amount of residue from the desired signal. You should also be able to hear the effect of adjusting the attack and release parameters. Slower attack and release times allow more of the transients to leak into the noise monitor. Using faster attack and release times (or enabling the AUTO mode) retains more of the desired signal during transients, so that less transient signal leaks into the noise monitor signal. If the monitor signal contains a lot of low or mid frequencies from the desired signal, you should consider adjusting the frequency scaling parameters to prevent these frequencies from being removed as noise. Try reducing the amount and threshold parameters at these frequencies.

Although the monitor feature is useful, you should base your decisions on the sound of the processed signal, comparing this to the original sound when the plug is bypassed. Listening to the noise monitor by itself ignores the fact that many low level details of the noise reduction process are masked by the desired signal. Thus, details in the noise monitor signal may be inaudible in the processed signal.

### Spectrum display

MR Noise features a spectrum display which is shown below.



Figure 6-5. Noise reduction spectrum display. Green is input signal spectrum, red is output signal spectrum, and yellow is the noise floor spectrum. For stereo inputs, the left channel is displayed on top, and the right channel is displayed below.

When processing a stereo signal, the display is divided into two sections; the top display is the left channel and the bottom display is the right channel. For greater detail you can look at just one channel by using the DISP MODE control. DISP MODE has values of "Stereo", "Left", and "Right". Use the Left or Right values to select just the left and right channels for display. When processing mono signals the DISP MODE control will show "Mono" and the display will show the single channel.

In the display, the input signal spectrum is shown in green, the output signal spectrum is shown in red, and the noise floor spectrum is shown in yellow. The input and output spectra are shown only when the MR Noise is enabled and the plug-in is processing audio.

<b>Green</b>	Input signal spectrum
<b>Red</b>	Output signal spectrum
<b>Yellow</b>	Noise floor spectrum

MR Noise uses a fairly short spectral analysis time, under 20 milliseconds, and consequently the spectrum display does not have good resolution at low frequencies. This is seen in the spectrum display as a very smooth curve at low frequencies. The choice of using a short analysis time was made to optimize the noise reduction performance, without regard to display resolution.

### Editing the noise floor

It may be impossible to find a portion of sound that contains only background noise. In this case, the noise floor can be learned from a portion of your sound that



## 6. MR Noise

has the lowest signal level, and then you can manually adjust the floor by editing. To edit the noise floor, click on the FLOOR button.



Figure 6-6. Clicking the floor button allows the noise floor to be edited manually. Click the floor button again to turn off editing.

When the FLOOR button is lit, a set of 31 control points are drawn on each of the stereo noise floor curves. The curves can then be modified by clicking and dragging the control points. As shown in Figure 6-5 it is also possible to click and drag a selection window to select multiple points. You can also SHIFT-click on points to select any set of points. Note that when LEARN is enabled (button lit) the noise floors cannot be edited until learning is complete. After editing you may want to save a preset to save your noise floor edits. Click the floor button again to turn off editing. When the FLOOR button is lit, clicking RESET will reset the noise floor to -160 dB at all frequencies.




Figure 6-7. Editing the noise floor. Clicking and dragging will select multiple points. The selected points are highlighted.

### Editing the frequency scaling curves

For challenging noise reduction problems, it may be useful to specify different threshold, amount, attack time, and release time parameters at different frequencies. This can be done by scaling the parameters as a function of frequency. MR Noise allows the user to specify a scaling curve for each of the above parameters. To edit the scaling curve, click on the corresponding edit button. The figure below shows the Amount button selected.



Figure 6-8. The Amount parameter is selected for editing as a function of frequency.

## Wave Arts Master Restoration Suite

When one of the parameter buttons is selected, a blue scaling curve is drawn on the display. The scaling curve is specified using 11 control points at frequencies from 20 Hz to 20 kHz such that each point spans roughly one octave. Each control point can scale the parameter from 0% to 200% of the parameter's nominal value. The parameter value at any frequency is determined by the product of the value shown on the knob times the value of the scaling curve at that frequency. The figure below shows an example scaling curve. Although the display is stereo, the scaling curves are monophonic; the scaling parameters are the same for each channel. If you click RESET when editing a scaling curve, the curve will be reset to x1 at all frequencies.




Figure 6-9. Example scaling curve for the Amount parameter. Frequencies below 160 Hz are at 50% value. If the Amount knob was set to 12 dB, then Amount would be 6 dB up to 160 Hz, and 12 dB above 320 Hz.

## 6.4 Parameters

The table below lists all the internal parameters of MR Noise and shows the range of values as would be displayed by a generic parameter-value plug-in interface, or by an automation interface. Most of these parameters have a one to one correspondence with controls on the user interface.

Parameter name	Values
Enable	0 = Off, 1 = On
Monitor Enable	0 = Off, 1 = On
Threshold	0 – 40 dB
Amount	0 – 60 dB
Attack Time	0 – 100 msec
Release Time	0 – 1000 msec
Knee Type	0 = Soft, 1 = Medium, 2 = Hard
Learn Enable	0 = Off, 1 = On
Learn Time	0 = 50 msec, 1 = 100 msec, 2 = 200 msec, 3

## 6. MR Noise

	= 500 msec, 4 = 1 sec, 5 = 2 sec, 6 = 5 sec, 7 = manual
Auto Mode	0 = Off, 1 = On
Gain	-12 dB to +12 dB
Monitor Gain	-12 dB to +12 dB
Left Floor 0-30	-160 to 0 dB
Right Floor 0-30	-160 to 0 dB
Thresh Scale 0-10	0 to 2
Amount Scale 0-10	0 to 2
Attack Scale 0-10	0 to 2
Release Scale 0-10	0 to 2

The parameters are described in more detail below.

**Enable** — Enables or bypasses the noise reduction processing.

**Monitor Enable** — This enables/disables the monitor feature. When monitoring is enabled, the output signal consists of the noise signal that is removed by MR Noise.

**Threshold** — Sets the amount the noise floor is offset to start signal attenuation at higher levels than the noise floor. The threshold raises the knee point above the noise floor.

**Amount** — Sets the amount of noise reduction in dB. This is the maximum amount of attenuation for signals that are at or below the noise floor level.

**Attack Time** — This parameter sets the attack time constant of the dynamics processor for each frequency, that is, how fast a signal can increase at each frequency. A time of 0 means attacks are followed as quickly as possible. Longer time constants cause smoothing of attacks.

**Release Time** — This parameter sets the release time constant of the dynamics processor for each frequency, that is, how fast a signal can decay at each frequency. A time of 0 means releases are followed as quickly as possible. Longer time constants cause smoothing of decays.

**Knee Type** — The Knee determines how fast the attenuation is applied as the signal approaches the noise floor. The Soft knee applies attenuation slowly, Medium is a sharper transition, and Hard is the hardest transition.

**Learn Enable** — Enables learning. When learning is enabled, the input signal spectrum is averaged to form the noise floor spectrum.

**Learn Time** — Sets the learn time from 50 msec to 5 seconds. Learning will automatically stop after the learn time period. Manual learning means the learn enable must be turned off manually to stop learning.

## Wave Arts Master Restoration Suite

**Auto Mode** — When enabled, Auto mode overrides the attack and release times with automatically determined times based on a broadband transient analysis. MR Noise will use fast attacks during rapid onsets and will use fast releases during rapid offset events. During slowly changing signals without transients, the usual attack and release times are used for maximum smoothness.

**Gain** — Output gain in dB.

**Monitor Gain** — Monitor output gain in dB.

**Left Floor** – Noise floor levels in dB for the left channel. There are 31 floor parameters ranging from 20 Hz to 20 kHz in roughly 1/3-octave intervals.

**Right Floor** - Noise floor levels in dB for the right channel. There are 31 floor parameters ranging from 20 Hz to 20 kHz in roughly 1/3-octave intervals.

**Thresh Scale** – Frequency scaling values for the Threshold parameter ranging from x0 to x2. There are 11 scaling parameters ranging from 20 Hz to 20 kHz in roughly one-octave intervals.

**Amount Scale** – Frequency scaling values for the Amount parameter ranging from x0 to x2. There are 11 scaling parameters ranging from 20 Hz to 20 kHz in roughly one-octave intervals.

**Attack Scale** – Frequency scaling values for the Attack Time parameter ranging from x0 to x2. There are 11 scaling parameters ranging from 20 Hz to 20 kHz in roughly one-octave intervals.

**Release Scale** – Frequency scaling values for the Release Time parameter ranging from x0 to x2. There are 11 scaling parameters ranging from 20 Hz to 20 kHz in roughly one-octave intervals.

## 6.5 Presets

Following is the list of presets that ship with MR Noise.

Name	Description
Default	Default settings, same as Clean
Clean	Default settings with learn enabled
Light Clean	Light cleaning settings with learn enabled
Vinyl	Vinyl phonograph settings with reduced threshold and amount at low frequencies, learn enabled
Tape	Magnetic tape settings, harder knee than Clean, learn enabled.
LP33 Floor	Example vinyl phonograph noise floor
Cassette Floor	Example cassette tape noise floor

## 6.6 Specifications

<b>Description</b>	Frequency domain noise reduction processor
<b>Platforms</b>	Pentium & compatible; PowerPC
<b>Operating Systems</b>	Windows 2000/XP; Mac OS X 10.4 or higher
<b>Plug-in Formats</b>	AU, DirectX, MAS, RTAS, VST
<b>Sampling Rates</b>	up to 192 kHz, supported rates listed below
<b>Precision</b>	32-bit processing
<b>Latency</b>	20 milliseconds or less, depending on sampling rate, listed below
<b>I/O Formats</b>	mono-mono, stereo-stereo

MR Noise is designed to work at the sampling rates listed in the table below. When processing audio at some other sampling rate, the closest sampling rate in the table below will be chosen. The table also lists the processing latency in samples and milliseconds for each sampling rate.

<b>Sampling rate</b>	<b>Latency, samples</b>	<b>Latency, msec</b>
8000	160	20
11025	160	14.5
16000	320	20
22050	320	14.5
32000	640	20
44100	640	14.5
48000	640	13.3
88200	1280	14.5
96000	1280	13.3
176400	2560	14.5
192000	2560	13.3



## 7. MR Gate



Figure 7-1. MR Gate user interface.

### 7.1 Overview

MR Gate is a full featured expander/gate that can be used to gate noise during quiet sections. Some of MR Gate's key features are:

- Adjustable lookahead
- Comprehensive metering
- Dynamic display shows recent history of input and gain levels
- Monitor allows you to hear gated signal

A diagram of MR Gate's audio routing and meter placement is shown below.




Figure 7-2. MR Gate audio routing diagram.

In normal processing, the gate mutes the audio during silent portions. When the monitor feature is enabled, the output consists of the low level signal that is removed by the gate.

### 7.2 About Gating

A noise gate is a conceptually simple device that passes high level signals and attenuates low level signals. This is useful for muting the noise that can be heard in the quiet sections between loud parts. A gate monitors the level of the input signal, and if the level falls below a predetermined threshold, the signal is attenuated. The threshold is set to be just above the level of the background noise.

The amount of attenuation applied depends on the ratio control. The definition of ratio is somewhat confusing. A ratio of 1 means no attenuation is applied as signals fall below threshold, while a ratio of infinity means the signal is maximally attenuated. For other ratios  $R$ , the attenuation is  $(R-1)$  times the difference between the input signal and the threshold. So for example, if the ratio is 5 and the signal is 10 dB below threshold, then 40 dB of attenuation will be applied. MR Gate has a maximum ratio of 50 which for practical purposes can be considered infinite. Because MR Gate has a ratio control it is more properly considered to be an “expander” than a gate.

The attack and release time parameters control how fast gain changes are applied. The release time controls how fast the gain is turned down and the attack time controls how fast the gain is restored. Consider the example of a drum recording containing background noise, assuming the threshold has been set just above the background noise and the ratio is large. When the signal goes below threshold the gate kicks in and begins reducing gain. A short release time will decrease gain rapidly, abruptly cutting off the decay of the drum. Longer release times cause the gain to decrease more slowly, which may sound more natural but also allow the noise to be audible at the end of the drum decay. On the next drum hit, the gate will restore gain according to the attack time. Using a short attack time is prudent in this case, otherwise the attack of the drum will be lost due to the slow attack fade-in of the gate. So, when gating, the attack and release times correspond to the attack and release times of the instrument you are processing.

Another important parameter for gating is the lookahead time. Lookahead allows the gate to respond to events in the signal before they occur. This is done by delaying the audio signal after level detection and before gain processing. Lookahead is particularly important for restoring gain just before onset (attack) events. A few milliseconds of lookahead is sufficient to allow the gain to ramp up before the attack is processed by the gain stage. Running a gate without lookahead risks cutting off all attack events.

#### MR Gate Input and Gain meters

MR Gate displays an input meter on the left and a gain reduction meter on the right. The input meter shows the peak signal level coming into the gate and the gain reduction meter shows the amount of gain reduction being applied.



## 7. MR Gate




Figure 7-3. MR Gate input meter (left) and gain reduction meter (right).

The meters show both the minimum and maximum values since the last meter redraw. The meter is drawn with a dark color up to the minimum value, and drawn with a lighter color from minimum to maximum value. These types of meters are a Wave Arts innovation. The “min/max” meters let you see at a glance how much the signal is modulating. If the signal level is constant the meter bar will be a solid dark color. If the signal level is modulating rapidly, this is shown by a large light section. The size of the light section indicates how much a signal is changing dynamically.

The input meter has a triangular control that lets you set the input threshold level. Drag the control up and down to change the threshold.

### MR Gate display



Figure 7-4. MR Gate time display. The green plot is the input signal level, the blue plot is the gate gain, and the yellow line is the threshold.

MR Gate features a dynamic display that plots signal level and the gate gain. The MR Gate display is shown above. Signal level is plotted in green, the gate gain is plotted in blue, and the threshold level is plotted as a horizontal yellow line. The display is mono for either mono or stereo inputs. This is because when processing stereo inputs, MR Gate applies the same gain to both channels based on peak level calculated across both channels. The display is only active if MR Gate is enabled.

## Wave Arts Master Restoration Suite

The display plots the last few seconds. As processing continues, the display contents scroll from right to left. The vertical amplitude axis range can be changed by right-clicking (SHIFT-clicking on Mac) the vertical axis; this will display a popup menu of choices for vertical axis range. Similarly the horizontal time axis range can be changed by right clicking (SHIFT-clicking on Mac) the horizontal axis; this will display a popup menu of choices for horizontal axis range.

### 7.3 Using MR Gate

A good place to start is to select the "Fast Gate" preset. If you are using the Master Restoration plug-in, click on the DISPLAY button to bring up the MR Gate display. Now start playback and adjust the threshold to be just above the level of the background noise during quiet sections. After the threshold is set, you may want to adjust the release time to get the most natural sounding decays into silence. For best results you want to match the release time of the gate with the release time of the sound you are gating.

If the noise gating is too obtrusive, you may want to reduce the attenuation during quiet sections. This can be done by using lower ratio values.

Selecting the MONITOR button allows you to hear the sound that has been removed by the gate. Typically this will contain background noise, and perhaps some reverberant decay tail from the sound you are gating. If you hear the leading portions of sound onsets, you may want to increase the lookahead time to prevent these from being gated.

### 7.4 Parameters

The table below lists all the internal parameters of MR Gate and shows the range of values as would be displayed by a generic parameter-value plug-in interface, or by an automation interface. Most of these parameters have a one to one correspondence with controls on the user interface.

Parameter name	Values
Enable	0 = Off, 1 = On
Monitor Enable	0 = Off, 1 = On
Ratio	1 to 50 (1:1 to 1:50)
Threshold	-72 to 0 dB
Attack	0.1 to 1000 msec
Release	1 to 2000 msec
Lookahead	0 = off, 1 = 1 msec, 2 = 2 msec, 3 = 5 msec
Knee	0 = Soft, 1 = Medium, 2 = Hard
Gain	-12 to +12 dB
Monitor Gain	-12 to +12 dB

The parameters are described in more detail below.

## 7. MR Gate

**Enable** - Enables/bypasses MR Gate. In the standalone MR Gate plug-in, this parameter is implemented with the bypass control. In the Master Restoration plug-in, this parameter is implemented with the ENABLE button.

**Monitor Enable** - Enables/disables monitoring. When monitoring is enabled, the output signal contains only the signal that is being removed (gated).

**Ratio** - Controls the amount of attenuation. Higher ratios cause more attenuation as the signal falls below threshold.

**Threshold** - Input signals are attenuated when they fall below the threshold level.

**Attack Time** - Sets the time it takes to increase gain.

**Release Time** - Sets the time it takes to decrease gain.

**Lookahead** - Sets the lookahead time. Lookahead is useful when gating to provide a bit more time for the gate to restore gain prior to an onset.

**Knee** - Sets the dynamics knee shape; options are soft, medium and hard.

**Gain** — Output gain in dB.

**Monitor Gain** — Monitor output gain in dB.

### 7.5 Presets

Following is the list of presets that ship with MR Gate.

Name	Description
Default	Default settings with MR Gate disabled
Fast Gate	Fast release gate
Slow Release Gate	Slow release gate
Medium Gate	Small ratio downward expander, use for medium ducking during silence
Mild Gate	Very small ratio downward expander, use for mild ducking during silence

### 7.6 Specifications

<b>Description</b>	Expander/gate
<b>Platforms</b>	Pentium & compatible; PowerPC
<b>Operating Systems</b>	Windows 2000/XP; Mac OS X 10.4 or higher
<b>Plug-in Formats</b>	AU, DirectX, MAS, RTAS, VST

## Wave Arts Master Restoration Suite

<b>Sampling Rates</b>	up to 192 kHz
<b>Precision</b>	32-bit processing
<b>Latency</b>	0-5 msec depending on lookahead setting
<b>I/O Formats</b>	mono-mono, stereo-stereo

## 8. Master Restoration



Figure 8-1. Master Restoration user interface.

### 8.1 Overview

Master Restoration combines the functions of MR Hum, MR Click, MR Noise, and MR Gate into one plug-in. The audio routing diagram for Master Restoration is shown below.




Figure 8-2. Master Restoration routing diagram.

## Wave Arts Master Restoration Suite

The signal processing order is MR Hum, MR Click, MR Noise, and MR Gate. When any of the processors is monitored, the output consists of a mix of all the monitor outputs from the processors. Hence, you can monitor any combination of the processors to hear a mix of all the signals that have been removed by the individual processors.

## 8.2 Using Master Restoration

The individual processors are described in detail in the preceding chapters, and the descriptions will not be repeated here. This section will describe some issues specific to using Master Restoration.

### Switching the display.

The processors share the same common display area. There are three ways to switch the active display:

1. Click on the tabs at the bottom of the display,
2. Click on the DISPLAY button in each section
3. Click on the panel in each section.

### Monitoring sections

Each section has a MONITOR button which can be selected to hear the signal that is removed by the processor. In Master Restoration, it is possible to select multiple sections to be monitored, in which case the output contains a mix of the monitored sections. Master Restoration keeps has separate gains for monitored and non-monitored output. Hence, when monitoring, you can increase the output gain control to more easily hear the monitor signal. When monitoring is turned off, the normal output gain is applied.

### Section presets

In Master Restoration, each section has a preset control as shown below. Click on the button to advance to the next section preset (SHIFT-click moves backwards to the preceding preset). Click on the text area to display a popup menu of preset options. There are rolloff menus for factory and user presets, and Save and Save As options for saving a section preset. This menu works like the main preset menu in the menu bar, which is described in Chapter 3.



Figure 8-3. Section preset control.

## Sharing presets between processors

User presets created in the various processor sections of Master Restoration are automatically imported into the individual plug-ins. Simply save the preset using the section preset control, then you will see this preset in the main preset menu of the individual plug-in. For example, if you save a preset in the Noise section of Master Restoration, this preset will be available in the MR Noise main preset menu, under the User rolloff menu. Similarly, if you save a preset in MR Noise, this preset will automatically appear in the preset control of the Noise section of Master Restoration.

## 8.3 Presets

Master Restoration factory presets are listed in the table below.

Name	Description
Default	Default settings with nothing enabled
Tape clean	Magnetic tape
Vinyl clean	Vinyl phonograph

## 8.4 Specifications

<b>Description</b>	Hum, buzz, click, crackle, and broadband noise removal with gating, brickwall filters, and spectrum analysis
<b>Platforms</b>	Pentium & compatible; PowerPC
<b>Operating Systems</b>	Windows 2000/XP; Mac OS X 10.4 or higher
<b>Plug-in Formats</b>	AU, DirectX, MAS, RTAS, VST
<b>Sampling Rates</b>	up to 192 kHz
<b>Precision</b>	64-bit hum and brickwall filters, 32-bit buzz filtering, 32-bit click and crackle removal, 32-bit noise reduction, 32-bit gating
<b>Latency</b>	Sum of latency of individual sections. See specifications for individual plug-ins.
<b>I/O Formats</b>	mono-mono, stereo-stereo





# License Agreement

## END-USER LICENSE AGREEMENT FOR WAVE ARTS SOFTWARE

**IMPORTANT-READ CAREFULLY:** This Wave Arts End-User License Agreement ("EULA") is a legal agreement between you (either an individual or a single entity) and Wave Arts, Inc. ("Wave Arts") for the Wave Arts software accompanying this EULA, which includes computer software and may include associated media, printed materials, and "on-line" or electronic documentation ("SOFTWARE PRODUCT" or "SOFTWARE"). By exercising your rights to make and use copies of the SOFTWARE PRODUCT, you agree to be bound by the terms of this EULA. If you do not agree to the terms of this EULA, you may not use the SOFTWARE PRODUCT.

### SOFTWARE PRODUCT LICENSE

The SOFTWARE PRODUCT is protected by copyright laws and international copyright treaties, as well as other intellectual property laws and treaties. The SOFTWARE PRODUCT is licensed, not sold.

**GRANT OF LICENSE** This EULA grants you the following rights:

**Installation and Use.**

You may install and use the SOFTWARE PRODUCT on up to three computers, provided you are the only user. A license must be acquired for each individual user of the SOFTWARE PRODUCT.

**Reproduction and Distribution.**

You may not reproduce or distribute the SOFTWARE PRODUCT except to make backup copies, or to install as provided for above.

### DESCRIPTION OF OTHER RIGHTS AND LIMITATIONS

**Limitations on Reverse Engineering, Decompilation, and Disassembly.**

You may not reverse engineer, decompile, or disassemble the SOFTWARE PRODUCT, except and only to the extent that such activity is expressly permitted by applicable law notwithstanding this limitation.

**Software Transfer.**

You may permanently transfer all of your rights under this EULA, provided you retain no copies, you transfer all of the SOFTWARE PRODUCT, and the recipient agrees to the terms of this EULA.

## **Wave Arts Master Restoration Suite**

### **Termination.**

Without prejudice to any other rights, Wave Arts may terminate this EULA if you fail to comply with the terms and conditions of this EULA. In such event, you must destroy all copies of the SOFTWARE PRODUCT and all of its component parts.

### **COPYRIGHT**

All title and copyrights in and to the SOFTWARE PRODUCT (including but not limited to any images, text, and "applets" incorporated into the SOFTWARE PRODUCT), the accompanying printed materials, and any copies of the SOFTWARE PRODUCT are owned by Wave Arts or its suppliers. The SOFTWARE PRODUCT is protected by copyright laws and international treaty provisions. Therefore, you must treat the SOFTWARE PRODUCT like any other copyrighted material.

### **LIMITED WARRANTY**

**NO WARRANTIES.** Wave Arts expressly disclaims any warranty for the SOFTWARE PRODUCT. The SOFTWARE PRODUCT and any related documentation is provided "as is" without warranty of any kind, either express or implied, including, without limitation, the implied warranties or merchantability, fitness for a particular purpose, or noninfringement. The entire risk arising out of use or performance of the SOFTWARE PRODUCT remains with you.

**NO LIABILITY FOR CONSEQUENTIAL DAMAGES.** In no event shall Wave Arts or its suppliers be liable for any damages whatsoever (including, without limitation, damages for loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the use of or inability to use this Wave Arts product, even if Wave Arts has been advised of the possibility of such damages. Because some states/jurisdictions do not allow the exclusion or limitation of liability for consequential or incidental damages, the above limitation may not apply to you.

### **MISCELLANEOUS**

If you acquired this product in the United States, this EULA is governed by the laws of the State of Massachusetts.

If this product was acquired outside the United States, then local laws may apply.

# Support

For assistance, please send email to:

[support@wavearts.com](mailto:support@wavearts.com)

If you are having problems with a plug-in, please include the following information: plug-in name, operating system, and host software you are using. The version numbers are also helpful.

For software updates, revision history, frequently asked questions (FAQ), and more, please visit our website at:

[www.wavearts.com](http://www.wavearts.com)

Contact information:

Wave Arts, Inc.  
99 Massachusetts Ave.  
Arlington, MA 02474

tel: +1 781-646-3794  
fax: +1 781-646-7190



# Index

## A

A/B buffers .....17  
 About.....20  
 Acoustic noise .....42  
 Amount ..... 43, 46  
 Attack time .....44, 47, 56  
 Auto mode.....47

## B

Brickwall filter ..... 27, 28  
 Broadband noise.....42  
 Buttons .....15  
 Buzz ..... 27, 30  
 Bypass .....17

## C

Clicks ..... 34, 37  
 Copy .....17  
 Crackle..... 34, 37

## D

Demo mode ..... 7  
 Display ..... 28, 36, 47, 57

## E

Export preset .....20

## F

Factory presets.....18  
 Floor .....42, 45, 49

## G

Gating.....56

## H

Harmonics ..... 25, 29  
 Highpass filter .....27  
 Hum ..... 25, 29

## I

Import preset ..... 19, 63  
 Installation ..... 5

## K

Key code ..... 9  
 Knee .....43  
 Knobs .....13

## L

Latency .....32, 40, 53, 60, 63  
 Learn .....43, 45  
 Lookahead ..... 56  
 Lowpass filter ..... 27, 35

## M

Mac OS-X..... 5  
 Machine ID..... 8  
 Magnetic tape..... 42  
 Master Restoration ..... 61  
 Menu bar ..... 17  
 Meters ..... 15, 56  
 Monitor..... 29, 30, 37, 47, 58, 62  
 MR Click ..... 33  
 MR Gate ..... 55  
 MR Hum ..... 24  
 MR Noise ..... 41  
 Musical noise..... 44, 46

## N

Noise ..... 42

## O

Onset..... 35, 37

## P

Phonograph.....34, 37, 42  
 Preset menu..... 18  
 Preset name..... 18  
 Presets .....18, 62, 63

## R

Ratio ..... 56  
 Registration ..... 7  
 Release time .....44, 47, 56  
 Reset ..... 49, 50

## S

Save preset..... 19  
 Scaling ..... 49  
 Section preset ..... 62  
 Selector button ..... 14  
 Serial number..... 8  
 Sliders..... 15  
 Spectrum.....28, 42, 47

## Wave Arts Master Restoration Suite

### ***T***

Text entry .....	13
Threshold .....	44, 56
Tools menu .....	20

### ***U***

Undo .....	17
Unlock .....	7
User manual .....	21
User presets .....	19

